



Gulfstream

QUILT DESIGNED BY AGFstudio

Gulf Breeze

FABRICS DESIGNED BY BECCA PLYMALE



Fabric A
GBR-31502
CORAL COASTLINE




Fabric B
GBR-31501
PALM BREEZE



Fabric C
GBR-31508
SEAWEED GARDEN



Fabric D
GBR-31507
STRANDS OF HIBISCUS



Fabric E
GBR-31506
LAGOON DRIFT




Fabric F
GBR-31505
COASTAL JASMINE




Fabric G
GBR-31511
FLAMINGO PARADISE



Fabric H
GBR-31510
SAND DUNE TREASURES



Fabric I (Binding)
PE-426
APRICOT CREPE



BACKING
WIDE-10204
DECOSTITCH PEONY



FINISHED SIZE | 84½" x 84½"

FABRIC REQUIREMENTS

Fabric A	GBR-31502	¼ yd.
Fabric B	GBR-31501	¾ yd.
Fabric C	GBR-31508	1¼ yd.
Fabric D	GBR-31507	1⅝ yd.
Fabric E	GBR-31506	1⅝ yd.
Fabric F	GBR-31505	1⅝ yd.
Fabric G	GBR-31511	1¼ yd.
Fabric H	GBR-31510	⅝ yd.
Fabric I	PE-426	⅝ yd.

BACKING FABRIC
WIDE-10204 2⅝ yds (Suggested)

BINDING FABRIC
Fabric I PE-426 ⅝ yd. (Included)

CUTTING DIRECTIONS

¼" seam allowances are included.
WOF means width of fabric.

- Cut your templates following the diagram below.
- You should be able to fit nine (9) half hexies per WOF.




DIAGRAM 1

Fabric A

- Twenty two (22) half hexie template.

Fabric B

- Seventy two (72) half hexie template.

Fabric C

- Hundred and thirty six (136) half hexie template.

Fabric D

- Hundred and eighty (180) half hexie template.

Fabric E

- Hundred and eighty four (184) half hexie template.

Fabric F

- Hundred and eighty (180) half hexie template.

Fabric G

- Hundred and twenty eight (128) half hexie template.

Fabric H

- Sixty four (64) half hexie template.

Fabric I

- Eight (8) 2½" x WOF strips (Binding)

QUILT ASSEMBLY

Sew rights sides together.

- Place BACKING FABRIC on a large surface wrong side up. Stretch it with masking tape against that surface.
- Place BATTING on top of backing fabric.
- Place TOP on top of the batting with right side facing up. Smooth away wrinkles using your hands.
- Pin all layers together and baste with basting thread, using long stitches. You can also use safety pins to join the layers.
- Machine or hand quilt starting at the center and working towards the corners. Remember that quilting motifs are a matter of personal preference. Have fun choosing yours!
- After you finished, trim excess of any fabric or batting, squaring the quilt to proceed to bind it.

BINDING

Sew rights sides together.

- Sew eight (8) 2½" x WOF strips from fabric **I** to make a final strip 348" long. Start sewing the binding strip in the middle of one of the sides of the quilt, placing the strip right side down and leaving an approximated 5" tail. Sew with ¼" seam allowance (using straight stitch), aligning the strip's raw edge with the quilt top's raw edge.
- Stop stitching ¼" before the edge of the quilt (DIAGRAM B 1). Clip the threads. Remove the quilt from under the machine presser foot. Fold the strip in a motion of 45° and upward, pressing with your fingers (DIAGRAM B2). Hold this fold with your finger, bring the strip down in line with the next edge, making a horizontal fold that aligns with the top edge of the quilt (DIAGRAM B3). Start sewing at ¼" of the border, stitching all the layers. Do the same in the four corners of the quilt.

- Stop stitching before you reach the last 5 or 6 inches. Cut the threads and remove the quilt from under the machine presser foot. Lay the loose ends of the binding flat along the quilt edge, folding the ends back on themselves where they meet. Press them together to form a crease. Using this crease as the stitching line, sew the two open ends of the binding with right sides together (you can help yourself marking with a pencil if the crease is difficult to see).
- Trim seam to ¼" and press open. Complete the sewing. Turn binding to back of the quilt, turn raw edge inside and stitch by hand using blind stitch.
- If you are using our 2.5 edition (binding fabric), click or scan this QR code to see a tutorial on how to use this specialty fabric.

